




Chalmit
A Division of Hubbell Ltd.

PO Box 5575
Glasgow G52 9AP
Scotland

T +44 (0) 141 882 5555
F +44 (0) 141 883 3704
E info@chalmit.com
W www.chalmit.com

IMPORTING IES PHOTOMETRY INTO RELUX

1. Create a new or open up an existing project within Relux.
2. On the Main Menu bar, select the "Insert" tab, "Luminaires", then "New single luminaire..."
3. Select the "Individual luminaire" tab on the Product Selection window, and browse for the individual IES files that you wish to import, opening them one by one.



4. Select 'Add' to import the photometric file into your project.
5. For further assistance, please refer to the Relux help files.



Registered Office: Mitre House, 160 Aldersgate Street, London, EC1A 4DD
Registered Number: 669157

